

French

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (Fr) UNSHIFTED**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

$\langle$ 27e8	$\acute{\text{e}}$ 0026	$\textcircled{\text{a}}$ 0040	$\text{\"{a}}$ 0022	' 2019	(0028	$\text{\textcircled{S}}$ 00a7	$\text{\#}$ 002	! 002	* 002a	$\text{\~{a}}$ 007e 0	) 0029	- 002d	DEL
-------------------	----------------------------	----------------------------------	------------------------	--------------------	--------------------	----------------------------------	--------------------	-------------------	--------------------	-----------------------------	--------------------	--------------------	-----

TAB	α 03b1	ζ 03b6	ϵ 03b5	ρ 03c1	τ 03c4	θ 03b8	υ 03c5	ι 03b9	$\omicron$ 03bf	π 03c0	$[$ 005b	$]$ 005d	RET
-----	------------------	-----------------	--------------------	----------------	----------------	------------------	--------------------	-----------------	--------------------	---------------	-------------	-------------	-----

CAPS LOCK/ SHIFT	ϕ 03d9	σ 03c3	δ 03b4	φ 03c6	γ 03b3	η 03b7	ξ 03be	κ 03ba	λ 03bb	μ 03bc	$'$ 0027	$\backslash$ 005c	RET
------------------------	----------------	------------------	------------------	-------------------	------------------	----------------	---------------	------------------	-------------------	---------------	-------------	----------------------	-----

SHIFT		ς 03c2	χ 03c7	ψ 03c8	ω 03c9	β 03b2	ν 03bd	$,$ 002c	$;$ 003b	$\cdot$ 00b7	$=$ 003d	SHIFT
-------	--	---------------------	----------------	----------------	------------------	-----------------	---------------	-------------	-------------	-----------------	-------------	-------

SPACE

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

French

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (Fr) SHIFTED**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

> 27e9	or 1 0031	or 2 0032	or 3 0033	4 0034	5 0035	6 0036	7 0037	8 0038	9 0039	0 0030	¶ 00b6	— 005f	DEL
-----------	-------------------------	-------------------------	-------------------------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

TAB	Α 0391	Ζ 0396	Ε 0395	Ρ 03a1	Τ 03a4	Θ 0398	Υ 03a5	Ι 0399	Ο 039f	Π 03a0	{ 007a	} 007d	RET
-----	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

CAPS LOCK/ SHIFT	Ϟ 03d8	Σ 03a3	Δ 0394	Φ 03a6	Γ 0393	Η 0397	Ξ 039e	Κ 039a	Λ 039b	Μ 039c	^ 005e	 007c	RET
------------------------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	----------	-----

SHIFT		λ 03e0	Χ 03a7	Ψ 03a8	Ω 03a9	Β 0392	Ν 039d	? 003f	. 002e	/ 002f	+ 002b	SHIFT
-------	--	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-------



French

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (Fr) ALT-GR** (= right ALT = ALT+CONTROL)

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed border and background color are deadkeys: for the diacritic in red, press key once, then vowel key.
 Keys with bold border (and C above code point) are for combining diacritics: these are to be typed after the applicable character.
The combining acute 0301 is redundantly placed on the 6-key because the 1-key may have a conflicting system shortcut.

< 003c	' C 0301	` C 0300	~ C 0342	' C 0313	' C 0314	' C 0301	¨ C 0306	- C 0304	¨ C 0308				DEL
TAB	α 1fb3	ƒ 03dd	⇒ 03e1		† 2020	‡ 0371	¨ 0308	ˆ C0345			« 00ab	» 00bb	RET
CAPS LOCK/ SHIFT	Ń 03fb	Ć 03f2	Ț 0373	Ț 0372		ŋ 1fc3	Ј 03f3	Ѕ 03db	Њ 03d7	Ќ 03cf	“ 201c	— 2014	RET
SHIFT	' 02bc	ζ 03df	И 0377	' 0374	ω 1ff3	Β 03d0		‘ 2018	ˆ C0323	:			SHIFT

French

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (Fr) ALT-GR + SHIFT**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

C before code point number indicates combining characters (also marked by bold cell border), to be typed after the applicable character.

> 003e													DEL
-----------	--	--	--	--	--	--	--	--	--	--	--	--	-----

TAB	ΑΙ 1fbc	Φ 03dc	^	⋮ 205d	◡ 2312	⏏ 0370						⏏ 27e6	⏏ 27e7	RET
-----	------------	-----------	---	-----------	-----------	-----------	--	--	--	--	--	-----------	-----------	-----

CAPS LOCK/ SHIFT	Μ 03fa	Ϟ 03f9	— 2012	◡ 23d1	× 00d7	ΗΙ 1fcc	Ј 037f	Ϟ 03da	 2016		” 201d	— Ϟ 0305	RET
------------------------	-----------	-----------	-----------	-----------	-----------	------------	-----------	-----------	----------	--	-----------	-------------------------	-----

SHIFT		Ϟ 03de	И 0376	/, 0375	ΩΙ 1ffc		⏏ 230a	Ј 230b		— 2013		SHIFT
-------	--	-----------	-----------	------------	------------	--	-----------	-----------	--	-----------	--	-------

NOTE: the metrical caret symbol is input as U+0020, U+0020, U+032d