

UK

ISO Keyboard Pattern (non-US) Windows GreekKeysU 2015 (UK) UNSHIFTED

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

§ 00a7	1 0031	2 0032	3 0033	4 0034	5 0035	6 0036	7 0037	8 0038	9 0039	0 0030	- 002d	= 003d	DEL
-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

TAB	φ 03d9	ς 03c2	ε 03b5	ρ 03c1	τ 03c4	θ 03b8	υ 03c5	ι 03b9	ο 03bf	π 03c0	[005b	] 005d	RET
-----	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

CAPS LOCK/ SHIFT	α 03b1	σ 03c3	δ 03b4	φ 03c6	γ 03b3	η 03b7	ξ 03be	κ 03ba	λ 03bb	; 003b	' 2019	\ 005c	RET
------------------------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

SHIFT	# 0023	ζ 03b6	χ 03c7	ψ 03c8	ω 03c9	β 03b2	ν 03bd	μ 03bc	, 002c	. 002e	/ 002f	SHIFT
-------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-------

SPACE

UK

ISO Keyboard Pattern (non-US) Windows GreekKeysU 2015 (UK) SHIFTED

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

$\pm$ 00b1	or ! 0021	or @ 0040	or £ 00a3	\$ 0024	% 0025	or ^ 005e	or & 0026	or * 002a	or (0028	or) 0029	or 005f	or + 002b	DEL
---------------	-------------------------	-------------------------	-------------------------	------------	-----------	-------------------------	-------------------------	-------------------------	-------------------------	-------------------------	-----------------------	-------------------------	-----

TAB	Φ 03d8	λ 03e0	Ε 0395	Ρ 03a1	Τ 03a4	Θ 0398	Υ 03a5	Ι 0399	Ο 039f	Π 03a0	{ 007a	} 007d	RET
-----	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

CAPS LOCK/ SHIFT	Α 0391	Σ 03a3	Δ 0394	Φ 03a6	Γ 0393	Η 0397	Ξ 039e	Κ 039a	Λ 039b	· 00b7	" 0022	 007c	RET
------------------------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	----------	-----

SHIFT	~ 007e	Ζ 0396	Χ 03a7	Ψ 03a8	Ω 03a9	Β 0392	Ν 039d	Μ 039c	< 27e8	> 27e9	? 003f	SHIFT
-------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-------

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

UK

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (UK) ALT-GR** (= right ALT = ALT+CONTROL)

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed border and background color are deadkeys: for the diacritic in red, press key once, then vowel key.
 Keys with bold border (and C above code point) are for combining diacritics: these are to be typed after the applicable character.
The combining acute 0301 is redundantly placed on the 6-key because the 1-key may have a conflicting system shortcut.

# 0023	C 0301	C 0300	C 0342	C 0313	C 0314	C 0301	C 0306	C 0304	C 0308				DEL
TAB	<i>N</i> 03fb	<i>F</i> 03dd	<i>Æ</i> 03e1		† 2020	‡ 0371	<i>..</i> 0308	C 0345			« 00ab	» 00bb	RET
CAPS LOCK/ SHIFT	α 1fb3	Ϸ 03f2	Τ 0373	Τ 0372		η 1fc3	Ј 03f3	ς 03db	Ϸ 03d7		“ 201c	— 2014	RET
SHIFT	, 02bc	ζ 03df	и 0377	/ 0374	ω 1ff3	β 03d0	‘ 2018	’ 0027	Κ 03cf	C 0323			SHIFT

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

UK

ISO Keyboard Pattern (non-US) Windows GreekKeysU 2015 (UK) ALT-GR + SHIFT

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with bold border (and C above code point) are for combining diacritics: these are to be typed after the applicable character.

													DEL
TAB	Μ 03fa	Φ 03dc	^	⋮ 205d	ˆ 2312	Τ 0370					⏏ 27e6	⏏ 27e7	RET
CAPS LOCK/ SHIFT	ΑΙ 1fbc	Σ 03f9	— 2012	˘ 23d1	× 00d7	ΗΙ 1fcc	Ψ 037f	Ϛ 03da	 2016	: 003a	” 201d	— C0305	RET
SHIFT		Ϛ 03de	ϛ 0376	/, 0375	ΩΙ 1ffc		Λ 230a	Ψ 230b	< 003c	> 003e	— 2013	SHIFT	

NOTE: the metrical caret symbol is input as U+0020, U+0020, U+032d