

French Swiss

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (FrSwiss) UNSHIFTED**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

§ 00a7	1 0031	2 0032	3 0033	4 0034	5 0035	6 0036	7 0037	8 0038	9 0039	0 0030	' 0027	/ 0374	DEL
-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

TAB	φ 03d9	ς 03c2	ε 03b5	ρ 03c1	τ 03c4	ζ 03b6	υ 03c5	ι 03b9	ο 03bf	π 03c0	[005b	] 005d	RET
-----	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

CAPS LOCK/ SHIFT	α 03b1	σ 03c3	δ 03b4	φ 03c6	γ 03b3	η 03b7	ξ 03be	κ 03ba	λ 03bb	Τ 0373	' 2019	\ 005c	RET
------------------------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----

SHIFT	\ 005c	θ 03b8	χ 03c7	ψ 03c8	ω 03c9	β 03b2	ν 03bd	μ 03bc	, 002c	. 002e	- 002d	SHIFT
-------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-----------	-------

SPACE

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

French Swiss

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (FrSwiss) SHIFTED**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed borders and background color are deadkeys: for the diacritic in red (upper character in the cell), press key once, then vowel key. To type the (lower) character in black on those keys, press the key once followed by spacebar.

⋮ 003a	⋱ or +	⋱ or "	⋱ or *	⋱ !	⋱ %	⋱ &	⋱ /	⋱ (	⋱)	⋱ =	⋱ ?	⋱ /	DEL
	002b	0022	002a	0021	0025	0026	002f	0028	0029	003d	003f	037	

TAB	Φ	λ	Ε	Ρ	Τ	Ζ	Υ	Ι	Ο	Π	{	}	RET
	03d8	03e0	0395	03a1	03a4	0396	03a5	0399	039f	03a0	007a	007d	

CAPS LOCK/ SHIFT	Α	Σ	Δ	Φ	Γ	Η	Ξ	Κ	Λ	<	>		RET
	0391	03a3	0394	03a6	0393	0397	039e	039a	039b	27e8	27e9	007c	

SHIFT		Θ	Χ	Ψ	Ω	Β	Ν	Μ	;	·	?	SHIFT
	007c	0398	03a7	03a8	03a9	0392	039d	039c	003b	00b7	003f	

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

French Swiss

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (FrSwiss) ALT-GR** (= right ALT = ALT+CONTROL)

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

Keys with dashed border and background color are deadkeys: for the diacritic in red, press key once, then vowel key.
 Keys with bold border (and **C** above code point) are for combining diacritics: these are to be typed after the applicable character.
The combining acute 0301 is redundantly placed on the 6-key because the 1-key may have a conflicting system shortcut.

	C 0301	C 0300	C 0342	C 0313	C 0314	C 0301	C 0306	C 0304	C 0308				DEL
TAB	<i>N</i> 03fb	<i>F</i> 03dd	<i>Æ</i> 03e1		† 2020	‡ 0371	<i>..</i> 0308	C 0345			« 00ab	» 00bb	RET
CAPS LOCK/ SHIFT	α 1fb3	Ϸ 03f2	Τ 0372			η 1fc3	Ј 03f3	ς 03db	κ 03d7	Κ 03cf	“ 201c	— 2014	RET
SHIFT		ζ 03df	И 0377		ω 1ff3	β 03d0	‘ 2018	’ 0027	, 02bc	C 0323	— 2013		SHIFT

NOTE: The straight single quote U+0022 and double quote U+0027 may be changed automatically in Word unless you disable the option.

French Swiss

ISO Keyboard Pattern (non-US) **Windows GreekKeysU 2015 (FrSwiss) ALT-GR + SHIFT**

[THIS CHART DOES NOT SHOW THE FUNCTION KEYS.]

													DEL
TAB	M 03fa	F 03dc	^	⋮ 205d	⌒ 2312	⌞ 0370					⌈ 27e6	⌋ 27e7	RET
CAPS LOCK/ SHIFT	Α 1fbc	Σ 03f9	— 2012	⌒ 23d1	× 00d7	Η 1fcc	Ι 037f	Ϛ 03da	 2016	: 003a	” 201d	— C 0305	RET
SHIFT		Ϛ 03de	ϛ 0376		ω 1ffc		ι 230a	⌋ 230b	< 003c	> 003e		SHIFT	

--

NOTE: the metrical caret symbol is input as U+0020, U+0020, U+032d